CABLE TOTE BAG MISINA



Measurements: each panel 32cm large and 28cm high
Gusset 7cm wide
Skill Level: intermediate

How much yarn: 8 balls (each ball 50g and 100m) of **Misina** yarn (100% Virgin Wool) shade no. 31468
Hook: A 4.50mm crochet hook
Sewing needle: Yarn needle with rounded point
Other item: Lining fabric in the same colour
Mesh canvas 0.4mm

STITCHES
Using Hook: Chain (ch) – Double crochet (dc)
Half treble (htr) - Treble (tr) - Double treble (dhtr)
RIDGE HALF TREBLE BACK (RHTRB): work 1 htr inserting hook into back loop only of previous row.
FRONT POST TREBLE (RTRF): yarn on hook, insert hook around stem of treble from front to back, yarn on hook and pull through a loop, (yarn on hook and pull through two loops on hook) twice.
BACK POST TREBLE (RTRB): yarn on hook, insert hook around stem of treble from back to front, yarn on hook and pull through a loop, (yarn on hook and pull through two loops on hook) twice.
FRONT POST DOUBLE TREBLE (FPDTR): yarn on hook, insert hook around stem of treble from front to back, (yarn on hook and pull through a loop) twice, (yarn on hook and pull through two loops on hook) twice.
CABLE STITCH: (worked over 6 sts)
1st row: work 1 FPdtr into each of last 3 sts (i.e. 4th, 5th and 6th sts of cable), then work 1 FPdtr into each of first 3 sts passing behind the 3 sts just worked. **2nd and 4th row:** 6 RtrB. **3rd row:** 6 RtrF. Rep 1st- 4th row throughout.
RAISED STITCH: (worked over 10 sts)
1st row: work (2 RtrB, 2 RtrF) twice, 2 RtrB. **2nd row:** (2 RtrF, 2 RtrB) twice, 2 RtrF. Rep these 2 rows throughout.

TENSION
16 sts and 10 rows measure 10cm square over Cable and Raised stitch with 4.50 mm crochet hook. Take time to check tension before starting work: it is essential to work to the stated tension to achieve success.
Note: the stitches tend to draw the work in, so to achieve the correct dimensions, it is necessari to gently stretch the work and secure it onto the canvas mesh.

INSTRUCTIONS
Front Panel: ch60+ 3 turning ch, work 1 row of trebles, then continue as follows: 1 tr, (10 sts in Raised st, 6 sts Cable) 3 times, 10 sts in Raised st, 1 tr. When work measures 32cm from beg and 8 cable interweavings have been worked, fasten off.
Back Panel: work as Front Panel.
Base: commence with the number of chains needed to achieve a width of 32cm and work 6 rows of Ridge half treble back until work measures 7cm from beg. Fasten off.
Gussets: (make 2) for each gusset, commence with the number of chains needed to achieve a width of 7cm and work rows of Ridge half treble back until work measures 28cm from beg. Fasten off.

FINISHING
Place all parts onto the canvas mesh, adjusting them to size and securing them with a round of dc. Join gussets to base, inserting hook only into outer loops of both thicknesses for each stitch. Then join panels in the same manner. Line the bag, leaving a centimeter of fabric extending beyond the opening to create a decorative border, as shown in picture. Using the fabric, make two handles measuring 35x3cm each, then attach them to the panels, aligning them with the raised st bands and centering them between the cable motifs.

HAND WARMERS MISINA



Measurements: each mitten 18cm length and 22cm high
Skill Level: easy

How much yarn:
2 balls (each ball 50g and 100m) of **Misina** yarn (100% Virgin Wool) shade no. 31468
Hook: A 4.50mm crochet hook
Sewing needle: Yarn needle with rounded point

STITCHES
Using Hook: Chain (ch) – Half treble (htr)
RIDGE HALF TREBLE BACK (RHTRB): work 1 htr inserting hook into back loop only of previous row.

TENSION
16 sts and 10 rows measure 10cm square over Ridge half treble back with 4.50 mm crochet hook.

INSTRUCTIONS HAND WARMERS (make 2)
Ch40+ 2 turning ch, work 1 row of 40 half trebles, turn and cont to work rows of Ridge half treble back, until work measures 20cm from beg. Fasten off. Fold in half each mitten in the vertical direction and sew side seam, leaving a small 4cm opening for thumb 5cm from upper edge.